



Firing on A Gas Hob

A Must Keep

Product Review

Projects

by
Petra x

FIRING ART CLAY SILVER ON A GAS HOB

IMPORTANT! For proper and safe firing, please read this sheet thoroughly before starting.

1. Dry

Before firing, your piece must be completely dry. Dry it naturally, in a warm space, for more than a day, or with a hairdryer for at least 20 minutes.

- If the piece isn't dry, it may break or explode during firing, resulting in injury or burns.
- If you use a hair dryer, keep it close to the piece, until thoroughly dry.
- To check if the piece is completely dry, place the piece on stainless steel, glass or a plastic plate. After about 10 to 20 seconds remove the piece. If there is no water condensation on the plate you are using, the piece should be dry.

2. Trace outline

To check if your piece has been successfully fired, trace the outline of the unfired piece on a sheet of paper. Compare the fired piece with the traced size - Art Clay Silver contracts 8-10% in volume after firing so you should see a slight shrinkage.

3. Prepare bowl

To cool off the fired piece, prepare a bowl of water. The bowl should be made of stainless steel or glass.

4. Check glow

Place the stainless steel net over the burner. Make sure the stainless steel net is balanced and secure. Turn on the burner and find the hottest area of the net by its red glow. Turn it off.

5. Place on net

Immediately place the piece on the hottest part of the net using a pair of tweezers. If you have a protective net, place this over your piece.

6. Fire

Turn the burner back on. The piece will flame for a few seconds as the binder in the clay burns off. Soon the piece will begin to glow. It is easier to see this if you dim the lights. Fire for 5 minutes. For safety, don't move, or touch, your piece or the net.

7. Cool

After firing for 5 minutes, turn off the burner and let the piece cool on the net for about 15 minutes. If you try to remove the piece before it is cool it may stick to the net. When the piece is cool it will easily detach from the net.

8. Quench

After cooling for 15 minutes, pick up the piece with tweezers and dip it into water to cool it